Telemecanique Siemens PPI Protocol XBT N/R

09/2007





Table of Contents



	Safety Information	5
	About the Book	7
Chapter 1	Operating Principle. At a Glance General Information on Bus Communications. Operating Principle	9 10
Chapter 2	Software Configuration At a Glance Vijeo-Designer Lite Protocol - Siemens S7 PPI Dialog Box Configuring Equipment Addresses Equipment Address Dialog Box.	13 14 16 17
Chapter 3	Variable Types Supported	
Chapter 4	Cables and Connectors At a Glance Cables SUB-D25 Pin Connections	23 24
Chapter 5	Diagnostics	

Appendices		31
	At a Glance	31
Appendix A	RS485 Recommendations	33
	RS485 Recommendations	
Glossary		35
Index		37

Safety Information



Important Information

NOTICE

Read these instructions carefully, and look at the equipment to become familiar with the device before trying to install, operate, or maintain it. The following special messages may appear throughout this documentation or on the equipment to warn of potential hazards or to call attention to information that clarifies or simplifies a procedure.



The addition of this symbol to a Danger or Warning safety label indicates that an electrical hazard exists, which will result in personal injury if the instructions are not followed



This is the safety alert symbol. It is used to alert you to potential personal injury hazards. Obey all safety messages that follow this symbol to avoid possible injury or death.

A DANGER

DANGER indicates an imminently hazardous situation, which, if not avoided, **will result** in death or serious injury.

WARNING

WARNING indicates a potentially hazardous situation, which, if not avoided, **can result** in death, serious injury, or equipment damage.

A CAUTION


CAUTION indicates a potentially hazardous situation, which, if not avoided, **can result** in injury or equipment damage.

PLEASE NOTE

Electrical equipment should be installed, operated, serviced, and maintained only by qualified personnel. No responsibility is assumed by Schneider Electric for any consequences arising out of the use of this material.

© 2007 Schneider Electric. All Rights Reserved.

About the Book



At a Glance

Document Scope

This document describes the connection to and the communication with the Siemens PPI protocol for the XBT N/R product range.

Validity Note

The data and illustrations found in this document are not binding. We reserve the right to modify our products in line with our policy of continuous product development. The information in this document is subject to change without notice and should not be construed as a commitment by Schneider Electric.

Related Documents

Title of Documentation	Reference Number
XBT N/R/RT Instruction sheet	W916810140111 A07
XBT N/R/RT User Manual	33003962
Vijeo-Designer Lite	Online help

Product Related Warnings

Schneider Electric assumes no responsibility for any errors that may appear in this document. If you have any suggestions for improvement or amendments or have found errors in this publication, please notify us.

No part of this document may be reproduced in any form or by means, electronic or mechanical, including photocopying, without express written permission of Schneider Flectric

All pertinent state, regional and local safety regulations must be observed when installing and using this product. For reasons of safety and to ensure compliance with documented system data, only the manufacturer should perform repairs to components.

Since the XBT N/R terminals are not designed to pilot safety critical processes, no specific instructions apply in this context.

User Comments

We welcome your comments about this document. You can reach us by e-mail at techpub@schneider-electric.com

Operating Principle

1

At a Glance

Overview

This chapter describes the operating principle of XBT terminals in applications using the Siemens PPI protocol.

What's in this Chapter?

This chapter contains the following topics:

Topic	Page
General Information on Bus Communications	10
Operating Principle	11

33003992 09/2007

General Information on Bus Communications

Overview

The XBT terminals can be connected to PLCs using different protocols. This document describes the communication using the Siemens PPI protocol with the XBT terminal acting as client.

Tasks of XBT

The terminals are usually connected to a communication equipment (PLC or other) via a field bus. The XBT and the PLCs work autonomously of each other.

XBT terminals perform the following functions:

- monitoring function: XBT terminals visualize the processes that are active in the PLCs and indicate alarm states
- command function: XBT terminals send information to the PLC upon user request

Tasks of Buses

A bus system provides the possibility to connect different devices via a unique cabling.

Tasks of Protocols

The protocol defines the language that is spoken by all the equipment connected to the bus.

Operating Principle

Overview

The PPI protocol is one of the console link protocols for Siemens Simatic S7 and S7-S200.


This protocol is compatible with XBT N/R terminals.

Communications between a process controller's (or a computer's) processor and the XBT terminal using the PPI protocol are performed by exchanging messages in the directions point-to-point by means of an asynchronous serial link coupler.

The dialog between the higher processing levels and the XBT terminal is of the question/reply type. The requester (client station) transmits the messages to be executed to the server.

Note: The maximum number of bytes for an exchange is 218 (109 words). With the PPI protocol, the terminal communicates in RTU (Remote Terminal Unit) mode.

Example: operation with an XBT N401



The XBT has the status of client.

A WARNING


UNINTENDEND EQUIPMENT OPERATION

The protocol must be installed and used by authorized and properly trained peronnel.

Failure to follow these instructions can result in death, serious injury, or equipment damage.

A server's memory zone is accessed by means of the server's address.

Example: operation with an XBT N401



Software Configuration

2

At a Glance

Overview

This chapter contains the protocol parameters you must configure in the Vijeo-Designer Lite software for operating XBT terminals in Siemens PPI protocol applications.

What's in this Chapter?

This chapter contains the following topics:

Topic	Page
Vijeo-Designer Lite	14
Protocol - Siemens S7 PPI Dialog Box	16
Configuring Equipment Addresses	17
Equipment Address Dialog Box	19

33003992 09/2007

Vijeo-Designer Lite

Overview

Use the Vijeo-Designer Lite software to configure your XBT terminal for Siemens PPI protocol applications.

A WARNING

INCOMPATIBLE SOFTWARE

Use only Schneider Electric manufactured or approved software to program hardware.

Failure to follow these instructions can result in death, serious injury, or equipment damage.

Opening the Protocol -Siemens S7 PPI Dialog Box

To open the **Protocol - Siemens S7 PPI** dialog box in Vijeo-Designer Lite for setting the protocol parameters, proceed as follows:

tep	Action			
1	Start Vijeo-Designer Lite. To create a new application, continue w skip steps 2 and 3 and execute step 4.	ith step 2, if you have a	already create	ed a Siemens PPI application
2	From the application browser on the left Configuration → Terminal & Protoco Result: The following dialog box will be window.	ıl.	ŭ	
	APPLI1 Configuration Terminal & Protocol	Configuration Configuration Configuration Configuration Configuration	Resolution Screen Color Back-light Colo Peripherals Touch Screen Software Scrolling Alarm	2 Lines 20 Columns Black and White 1 Color No No
		Terminal Type XBT-N410	•	Terminal Protocol Siemens S7 PPI Apply Cancel
3	From the Terminal Protocol list in the Apply .	lower right corner sele	ect the item S	iemens S7 PPI and click
4	Select from the application browser the Result : The dialog box Protocol - Sien Designer Lite window where you can co	nens S7 PPI will be di	splayed on th	


33003992 09/2007

Protocol - Siemens S7 PPI Dialog Box

Purpose

Use this dialog box to configure the protocol parameters for Siemens PPI communication.

Representation



Elements of the dialog box

Element	Description
Protocol Specific	
XBT Address	Enter a unique address between 0 and 126 for the
	XBT terminal.

WARNING

UNINTENDED EQUIPMENT OPERATION

Set the address of the XBT terminal to a unique address.

Failure to follow these instructions can result in death, serious injury, or equipment damage.


Configuring Equipment Addresses

Overview

Use the Vijeo-Designer Lite software to configure addresses for the equipment your XBT terminal should communicate with.

Opening the Equipment Address Dialog Box

To open the **Equipment Address** dialog box in Vijeo-Designer Lite for configuring equipment addresses, proceed as follows:



33003992 09/2007

Step	Action
3	In the Equipments dialog box select a device from the list.
4	In the Equipment Settings \rightarrow Identification box below click the button right to the Address text box.
	Result: The dialog box Equipment Address will be displayed where you can configure an address for
	the selected equipment.


Equipment Address Dialog Box

Purpose

Use this dialog box to configure equipment addresses for your individual devices.

Representation

PPI equipment address



Elements of the dialog

Element	Description
CPU Number	Enter the CPU number (between 0 and 126) for the selected equipment.
OK button	Click the OK button to assign the entered address to the selected equipment.
Cancel button	Click the Cancel button to discard the changes and to close the dialog box.
Help button	Click the Help button to open the Vijeo-Designer Lite online help.

Variable Types Supported

Table of Variable Types Supported by the XBT

The following table lists all Siemens PPI variables XBT terminals can access:

Variable Type Supported	PPI Syntax	Identifiers
Bit	%Vi.j	• i: (0131070)
		• j: (015)
String	%VBi	i: (0131070)
Word	%VWi	i: (0131070)
Double Word	%VDi	i: (0131070)
Floating Point	%VDi	i: (0131070)

Note: The objects' addresses must belong to accessible memory zones which are specific to each type of process controller. The i indexes, which are always even, correspond to byte addresses in conformity with the Siemens MicroWin operating software convention.

Cables and Connectors

4

At a Glance

Overview

This chapter specifies the cables and connectors required for XBT terminals in Siemens PPI applications.

What's in this Chapter?

This chapter contains the following topics:

Topic	Page
Cables	24
SUB-D25 Pin Connections	25

Cables

Technical Data

The following table lists the cables required to connect XBT terminals to Siemens S7 PG PLCs.

XBT Terminal	Connected Device	Physical Link	Cable Reference	Length
• XBT N401/N410	Siemens S7 PG	RS485	XBTZ972	2.5 m
• XBT R410/R411			(SUBD25 <> SUBD9)	(8.2 ft.)


SUB-D25 Pin Connections

Overview


The following XBT terminals provide a SUB-D25 connector on their rear panels:

- XBT N401
- XBT N411
- XBT NU400
- XBT N410
- XBT R410
- XBT R411

The SUB-D25 connector supports RS232 as well as RS485 lines. The pin assignment is shown in the following figure.



Technical Data The illustration below shows the cabling for RS485 equipment.



Legend

- (1) Connection of the shielding at both ends depends on any electrical restrictions affecting the installation.
- (2) Rt: Line impedance resistor (typically 110 Ω). It is recommended to install the line impedance resistor with a RC circuit (R = 120 Ω /0.25 W and C = 1 nF/10 V min). Make sure that only one line impedance resistor is installed.

Note: RP resistors are integrated into the XBT and feature 4.7 k Ω for XBT N and 100 k Ω for XBT R.

XBT Error Indication

Overview

XBT terminals indicate errors in different ways

- by displaying question marks ?????? on alphanumerical fields
- by displaying crosses for graphic objects
- by displaying hash characters in alphanumerical fields
- by blinking alphanumerical fields
- by issuing error messages

The following paragraphs list these three errors and their possible reasons.

Question Marks and Crosses

When question marks ?????? and crosses XXXXXX are displayed on the display of your XBT terminal, a transmission error has occurred. To fix this error, check the following:

If	Then
question marks are displayed	verify that all cables are correctly connected.
question marks are displayed	the XBT terminal may have received no response from the
	PLC.

Hash Characters

Hash characters displayed in alphanumerical fields on your XBT terminal indicate that the value to be displayed is too long for this alphanumerical field and cannot completely be displayed. The value 100 can, for example, not be displayed in a 2-digit alphanumerical field. To fix this problem, enter a shorter value or adapt the size of the alphanumerical field so that it can display any of the possible values of the PLC variable.

Blinking Alphanumerical Fields

Blinking alphanumerical fields on your XBT terminal indicate that the value of this field has exceeded or fallen below a user-defined threshold.

Error Messages

A variety of error messages is by default configured for the terminals. All these standard system messages are assigned a panel number 200+x. A distinction is made between error messages indicating communication errors and error and status messages provoked by inputs at the terminal.

These 2 error message types differ by the numbers they are assigned and by the way they are displayed at the terminal as shown in the list below:

Error Message Caused by:	Error Message Numbers	Display Mode
Communication Errors	201–204	To indicate that a communication error has occurred, the error message is displayed in a popup dialog box every 10 seconds.
Input at Terminal	241 – 258	The error or status message is displayed as a response to user input at the terminal.

Error Messages Caused by Communication Errors

Errors 201 to 204 are error messages issued by the terminal to indicate that a communication error has occurred. They are displayed in a popup dialog every 10 seconds.

If	Then
error message 201: DIALOG TABLE AUTHORIZATION INCORRECT is displayed	the authorization word in the dialog table does not have the expected value. (Refer to the Vijeo-Designer Lite online help for information on how this word is working.) To solve this problem verify that: • you are connected to the right PLC • the memory of your PLC is not corrupted • the correct value is saved on the PLC
error message 202: DIALOG TABLE WRITING IMPOSSIBLE is displayed	the write cycle to the dialog table of the PLC could not be ended. This error may have the following causes: too much load on the communication bus EMC disturbances on the communication bus
error message 203: DIALOG TABLE READING IMPOSSIBLE is displayed	the read cycle from the dialog table of the PLC could not be ended. This error may have the following causes: too much load on the communication bus EMC disturbances on the communication bus

Error Messages Caused by Input at the Terminal

Errors 242 to 254 are error messages issued by the XBT terminal as a response to user input at the terminal. These messages are displayed directly after the operator has sent an incorrect command to the terminal and will persist until the user has corrected the entered command or value. Messages 255 to 258 are status messages displayed after the user has initiated an operation at the terminal to indicate that it has (or has not) been accepted and is in progress.

If	Then
error message 241: IMPOSSIBLE TO READ VARIABLE is displayed	the terminal has attempted to read a variable and could not get its value. This error may have the following causes: too much load on the communication bus EMC disturbances on the communication bus
error message 242: IMPOSSIBLE TO WRITE VARIABLE is displayed	the terminal has attempted to write in a memory area of the equipment and has received a negative acknowledgement or no acknowledgement at all. This error may have the following causes: too much load on the communication bus EMC disturbances on the communication bus
error messages 243 to 249 are displayed	correct the value or command you have entered as indicated by the error message.
error message 250: LANGUAGE IMPOSED BY PLC is displayed	the PLC forces the terminal to use a language. This language cannot be changed by the operator. For more information see the Vijeo-Designer Lite online help, functions of the dialog table.
error messages 251 or 252 are displayed	correct the value or command you have entered as indicated by the error message.
error message 253: PASSWORD IMPOSED BY PLC is displayed	you cannot change the password at the terminal because it is forced by the PLC. For more information see the Vijeo-Designer Lite online help, functions of the dialog table.
error message 254: PROTECTED ACCESS PAGE is displayed	you are trying to access a page that is password protected but you do not have the required authorization level.
error messages 255 to 258 are displayed	the commands you entered at the terminal are executed or not executed, as indicated in these status messages.

Diagnosis Counters

3 diagnosis counters can be displayed on the protocol's system panel (line parameters):

Counter	Meaning
1	number of responses received without any FCS error
2	number of responses received with an FCS error
3	number of requests that have not been answered

Note: The counters no. 4...8 are not used.

3003992 09/2007

Appendices



At a Glance

Overview

This chapter contains some RS485 recommendations.

What's in this Appendix?

The appendix contains the following chapters:


Chapter	Chapter Name	Page
Α	RS485 Recommendations	33

RS485 Recommendations



RS485 Recommendations

Diagrams for RS485 Link



- Maximum length for the link is 1,200 m (3,937 ft.).
- Wiring = 2 shielded twisted wires with a minimum cross-section of 0.6 mm² (AWG22) and one 0 V wire

Note: The maximum length including the RS485 link is 1,200 m (3,937 ft.), provided that the equipment connected to the XBT terminal is not subject to more stringent restrictions (refer to connected devices instruction sheet) and for XBT N200, XBT N400, XBT R400 and XBT RT500 provided that the length of the cable is below 10 m (32.8 ft.) (because power is also supplied by this cable).

Glossary



AWG American wire gauge (wire diameter)

FCS frame check sequence

M

Magelis Generic commercial name of the range of Schneider HMI terminals.

P

PLC programmable logic controller



RS485

recommended standard for connecting serial devices = EIA/TIA 485



Vijeo-Designer Lite

Configuration software for the low end Magelis range. It replaces the XBT-L1000 software.



XBT

Any HMI terminal (when it is not necessary to make a distinction).



Index

A	r
address	parameters, 13
configuring equipment address, 17	pin connections SUB-D25, 25
	PPI protocol
C	cables, 24
cables	data types, 21
PPI protocol, 24	diagnostics, 27
configuration	operating principle, 11
PPI protocol, 16	protocol configuration, 16
software parameters, 13	
	R
D	RS485
data tunas	recommendations, 33
data types PPI protocol, 21	recommendations, 66
diagnostics	_
PPI protocol, 27	S
111 protocol, 27	Siemens PPI protocol
_	operating principles, 10
E	SUB-D25
equipment address, 17	pin connections, 25
0	V
ahiaata	variable types
objects PPI protocol, 21	PPI protocol, 21
operating principle	Vijeo-Designer Lite, 14
PPI protocol, 11	. ,,55 = 55.g 5. =.10, 1 1
operating principles	
Siemens PPI protocol, 10	
· · · · · · · · · · · · · · · · · · ·	